




Hedging

Hedging section has two tab: Settings e Charts which will be analyzed.

Video Tutorial


	24/03/2016	Hedging - Cos'è l'hedging - Didattico	11:42
	24/03/2016	Hedging - Impostazioni	18:44
	24/03/2016	Hedging - Analisi	12:52

Click[here](#) **to watch other video** **Video di Iceberg**


Settings

In “Settings” is present the Wizard which allows the user to choose a hedging typology. On the right, the panel summarizes the settings .


The low section summarizes the strategy with leg, the payoff, the greeks course and the trades.





Il menu - Settings




Strategy

 Strategy	open the sub-menu Strategy
 New Strategy	it allows to create a new strategy
 Open Strategy	it allows to open a previous saved strategy
 Save Strategy	it allows to save the strategy in use
 Settings	open the window Strategy Settings for strategy settings









Edit

 Apply Changes	it confirm changes in Hedging settings
 Cancel Changes	it delete changes in Hedging settings


Hedging

 Enable Hedging	enable or disable Hedging
---	---------------------------

Charts

 Template	open the sub-menu "Template"
 Load Template	it allows to save the template of the payoff in use. If template is the configuration of the Payoff
 Save Template	it allows to load template previously saved and apply them to the payoff in use
 Save as Default	it allows to save template in use as default for the next payoff
 Reset Zoom & Pan	it allows to reset the zoom
 Cross Hair	it allows to enable or disable the Crosshair for the payoff
 Save as Image	it allows to save the payoff of the strategy in image format (*.png). The image will be saved to the Pictures folder of beeTrader, in the user's Documents
 Print	it allows to print the Payoff of Strategy currently in use. Feature available on the PC in use if there is a printer

Hedging Type



In “Hedging Type” the user can choose the hedging typology: Continuous or Threshold.

- **Continuous:** This type of hedging starts neutralizing Delta immediately and it buy/sell the instrument to maintain delta-zero for every price fluctuation. The advantage is that delta will be always next to zero. The disadvantage is that a huge amount of operations will be needed to maintain delta next to zero so we will have high costs of transactions and spreads. Continuous Hedging is usually used when the profit target is the free risk rate.
- **Threshold:** This type of hedging starts neutralizing Delta when underlying price reach to a threshold which is a price established by the user.

Legs to Hedge

Name	Threshold (ON Level)	Threshold (OFF Level)
Put @ 12 2016-06-17	11.99	12.01
Call @ 14 2016-06-17	14.01	13.99

Thresholds: underlying price levels that activate or deactivate hedging for each option.

Hedging system is Disabled

Previous Next

In the section “Legs to Hedge” you can choose the legs that you want to include in the calculation of the delta to protect.

Thresholds ON / OFF

Name	Protect
Put @ 11 2016-06-17	<input type="checkbox"/>
Put @ 12 2016-06-17	<input checked="" type="checkbox"/>
Call @ 14 2016-06-17	<input checked="" type="checkbox"/>
Call @ 15 2016-06-17	<input type="checkbox"/>

Select the legs you want to be hedged (one or more)

Hedging system is Disabled

Previous Next

In the section “Hedging Type” is selected Threshold mode, in Thresholds ON / OFF you can set the thresholds, for every legs, in which the hedging will be enabled(ON Level) or disabled (OFF Level).

Assets to Use

The screenshot shows the 'Assets to Use' configuration window. It features a table with two columns: 'Name' and 'Used to Hedge'. Two assets are listed: 'Eni SpA' and 'STOCK FUTURE Eni 17/06/2016', both with checked boxes in the 'Used to Hedge' column. To the right of the table are five buttons: 'Add Stock', 'Add Underlying Future', 'Add Other Future', 'Add ETF', and 'Add Option'. On the far right, a vertical sidebar contains several tabs: 'Hedging Type', 'Legs to Hedge', 'Thresholds ON / OFF', 'Assets to Use' (which is highlighted in green), 'Orders Type', 'Frequency', 'Data Filters', and 'Preview'. At the bottom of the window, there is a status bar that reads 'Hedging system is Disabled' and two buttons labeled 'Previous' and 'Next'.

In this section you can add the instrument (stocks, futures, options, ETF, etc.) to be used to neutralize delta.

Nota: se si utilizzano ETF per entrare in hedging è fondamentale che venga impostato l'ETF Ratio dell'ETF che si desidera utilizzare. Questo parametro, che si imposta in [Symbol Manager](#), indica il rapporto tra il sottostante e l'ETF: poniamo ad esempio che il sottostante sia il DJ EURO STOXX 50 che quota 2800 punti e l'ETF valga 28, l'ETF Ratio da impostare è 100. Questa vale per gli ETF Long, se si utilizzano ETF Short va impostato un valore negativo.

Orders Type

The screenshot shows the 'Orders Type' configuration window. It contains a table with the following data:

Hedge Order Direction	Contract Delta	Hedge Priority	Hedge Price Type	Hedge Use Smart Move	Hedge Smart Move Amount	Hedge Move
Long & Short	1.000	Macro Adjustment	MARKET	<input type="checkbox"/>	0	
Long & Short	500.000	Macro Adjustment	MARKET	<input type="checkbox"/>	0	

Below the table, there is a section for 'Orders Placement Mode' with a dropdown menu set to 'Paper Trading (Au...'. A descriptive text below reads: 'Smart Move: this function changes the order prices automatically. You can choose time period and price'. At the bottom, there is a status bar that reads 'Hedging system is Disabled' and two buttons labeled 'Previous' and 'Next'. The right sidebar is identical to the one in the previous screenshot, with 'Orders Type' highlighted in red.

- Name: it displays the instrument used for delta hedging and its settings;
- Order Direction: the user can choose the direction of order used to hedge the delta: Long, Short e Long & Short. This think is useful when options are used to hedge ;
- Contract Delta: it represents the delta value expressed in euro of one contract;
- Hedge Priority: The user can choose between Macro Adjustment and Fine Adjustment. Depending on the choice made by the user in the system will give priority to instruments indicated by Macro Adjustment to neutralize much of the delta and then use the instrument marked with Fine Adjustment to refine the delta hedging. If multiple instruments is associated with the same priority (Macro Adjustment and Fine Adjustment) the system will balance the delta dividing it evenly among the instruments. The most common use is to use futures as Macro Adjustment and stocks as Fine Adjustment;
- Order Type: the user can choose the type of order to use between Market, Join, Improve, Split, Shave, Hit & Take, Hit & Take +. For the description of [Orders Type](#), click [qui](#);
- Smart Move: the Smart Move system allows the sending of an order and the automatic change pf the price if it is not executed;
- Smart Move Amount (Ticks):it represents the price change between an order and the subsequent expressed in ticks;
- Smart Move Interval (secs): It represents the interval of time between an order and the next;
- Order Placement Mode: Here you choose how Iceberg must manage the delta hedging orders. Suggest Only: in this case the generation of an order in Iceberg is reported on the General tab, and the pending order is finalized in [Real Market](#) o [Paper Trading](#). Paper Trading (Automatic): In this case the generation of an order it is automatically finalized Paper Trading. Real Market (Manual): in this case the generation of an order appears the book corresponding to sending the order in Real Market. Real Market (Automatic): In this case the generation of an order is automatically sent to the broker with the price of the type previously set. **For any order, generation is conditioned to Date Filters.**

Frequency

Name	Hedge Min. Qty	Contract Delta	Contract Gamma	Contract Theta	Contract Vega	Contract Rho
Eni SpA	1	€ 1,00	€ 0,00	€ 0,00	€ 0,00	€ 0,00
STOCK FUTURE Eni 15/12/2017	1	€ 500,00	€ 0,00	€ 0,00	€ 0,00	€ 0,00

Delta 0 with tolerance ± Not Applicable

Setup the hedge frequency to avoid useless or too close corrections.

Hedging system is Disabled

Previous Next

This section allows to set the control frequency of the strategy's delta, or the system will calculate delta. Four modality are disponibile:

- Contracts: the system hedge the delta only after the specify number of contract definite in Hedge Min. Quantity is reached. It is possible to choose the minimum amount for every instrument ;
- Time Interval: the system checks whether is necessary hedge the delta every Time Interval

(minutes);

- Time of Day: The system checks whether is necessary hedge the delta in a determined hour of the day ;
- Price Change: The system checks whether is necessary hedge the delta after a % underlying price change .

Data Filters

There are available price filter in order to avoid problem with price exposed by the market maker .

- Max Bid/Ask Spread (Options): it verify that spread between bid and ask of the options in the strategy do not exceed a setted %;
- Tick is not Zero: It verify that last tick for every instrument of the strategy is not zero;
- Max. Tick Interval: it verify that time between a tick and the subsequent occurs within a certain time-range, for every strategy instrument;
- Check Bid/Ask (Underlyings):
- Check Last (Options):

As indicated a check on bid-ask option price price and on the last of the underlying is always effectuate in order to ensure the correct data flow between the broker and iceberg

Preview

Name	Contract Delta	Hedge Order Direction	Hedge Priority	Hedge Min. Qty	Qty	Hedge Qty
Eni SpA	1.000	Long & Short	Macro Adjustment	1	0	66
STOCK FUTURE Eni 17/0...	500.000	Long & Short	Macro Adjustment	1	0	0

Data Filters Results
 No Errors

Hedging system is Disabled

Previous

Next

A preview of the instruments used to hedge the delta and related quantity at market (Qty) and the quantity that should be used to neutralize the delta (Hedge Qty).

Charts

Iceberg records every hedging operation in order to premise the user to analyze the settings and to optimize the hedging strategy.



II menu - Charts

Strategy
 Settings
 Enable Hedging

TimeFrame

Leg

Option

TimeFrame

Bars Count

Strategy






Hedging

Delta Strategy Chart


Hedge Chart

Thresholds Analysis Chart

Strategy

 Strategy	Open the submenu strategy
 New Strategy	It allows to create a new strategy
 Open Strategy	It allows to open a strategy previously saved
 Save Strategy	It allows to save the strategy actually in use
 Settings	Open the window Strategy Settings for the strategy settings

Hedging

 Enable Hedging	enable or disable Hedging
--	---------------------------

Delta Strategy Chart

Timeframe	it is possible to choose the timeframe of the graph which represents the Delta
-----------	--


Hedge Chart

Leg	It is possible to choose the instrument for delta hedging, see the graph with profit/loss and the number of contract of delta hedging
-----	---

Thresholds Analysis


Option	It is possible to choose which option of the strategy the threshold are showed on the underlying graph
Timeframe	It is possible to choose which timeframe of the underlying graph the threshold are showed
Bars Count	It is possible to choose how many bars are showed in the underlying graph

Delta Strategy



In this graph is visualized the delta value of the hedging strategy since it was activated. From the menu you can choose the time frame of the graph.

Hedge Size



This graph shows the number of contracts used in every operations of hedging since hedging was activated. From the menu Hedge chart it is possible to choose, which instrument used to hedge is displayed .

Hedge In / Outcome



With reference to the chosen instrument in hedge Chart, in this graph are represented all profit / loss related to delta hedging operations.


Thresholds Analysis



In the graph is displayed Thresholds Analysis of the historical graph of the underlying (timeframe e bars count can be selected dal menù Thresholds Analysisi Chart) with the threshold set for the selected option in the menù Thresholds Analysis Chart.

This chart is very useful to analyze the position of the thresholds setted in relation to the number of times that have been touched.

Report



A useful report, accompanied by the underlying tick chart, it provides the user a clear view on the performance of its delta hedging settings.

From:

http://manuals.playoptions.it/Iceberg_old/ - **Iceberg Options Solutions**

Permanent link:

http://manuals.playoptions.it/Iceberg_old/en/hedging?rev=1472114872



Last update: **2016/08/25 10:47**