

Strategy - Hedging

Hedging section has two tab: Settings e Charts which will be analyzed.

Video Tutorial


	24/03/2016	Hedging - Cos'è l'hedging - Didattico	11:42	
	24/03/2016	Hedging - Impostazioni	18:44	
	24/03/2016	Hedging - Analisi	12:52	

Click [here](#) to watch other video **Video di Iceberg**


Settings

In “Settings” is present the Wizard which allows the user to choose a hedging typology. On the right, the panel summarizes the settings .



The low section summarizes the strategy with leg, the payoff, the greeks course and the trades.





II menu - Settings




Strategy

 Strategy	open the sub-menu Strategy
 New Strategy	it allows to create a new strategy
 Open Strategy	it allows to open a previous saved strategy
 Save Strategy	it allows to save the strategy in use
 Settings	open the window Strategy Settings for strategy settings









Edit

 Apply Changes	it confirm changes in Hedging settings
 Cancel Changes	it delete changes in Hedging settings


Hedging

 Enable Hedging	enable or disable Hedging
---	---------------------------

Charts

 Template	open the sub-menu "Template"
 Load Template	it allows to save the template of the payoff in use. Il template is the configuration of the Payoff
 Save Template	it allows to load template previously saved and apply them to the payoff in use
 Save as Default	it allows to save template in use as default for the next payoff
 Reset Zoom & Pan	it allows to reset the zoom
 Cross Hair	it allows to enable or disable the Crosshair for the payoff
 Save as Image	it allows to save the payoff of the strategy in image format (*.png). The image will be saved to the Pictures folder of beeTrader, in the user's Documents
 Print	it allows to print the Payoff of Strategy currently in use. Feature available on the PC in use if there is a printer


Hedging Type



In “Hedging Type” the user can choose the hedging typology: Continuous or Threshold.


- Continuous: This type of hedging starts neutralizing Delta immediately and it buy/sell the instrument to maintain delta-zero for every price fluctuation. The advantage is that delta will be always next to zero. The disadvantage is that a huge amount of operations will be needed to maintain delta next to zero so we will have high costs of transactions and spreads. Continuous Hedging is usually used when the profit target is the free risk rate.
- Threshold: This type of hedging starts neutralizing Delta when underlying price reach to a threshold which is a price established by the user.

Legs to Hedge




In the section “Legs to Hedge” you can choose the legs that you want to include in the calculation of the delta to protect.

Thresholds ON / OFF



In the section “Hedging Type” is selected Threshold mode, in Thresholds ON / OFF you can set the thresholds, for every legs, in which the hedging will be enabled(ON Level) or disabled (OFF Level).


Assets to Use



In this section you can add the instrument (stocks, futures, options, ETF, etc.) to be used to neutralize delta.

Nota: If you use an ETF as an hedging instrument you need to set the “ETF ratio” of that ETF. You set this parameter in [Symbol Manager](#). It denote the ratio between the underlying and the ETF. Take an example: The underlying is the dj Euro Stoxx 50 and it quote 2800 points, the ETF quote 28, the ETF ratio that you have to set is 100. This rule is valid for long ETF, whether the ETF is short you have to set a negative value.


Orders Type



- Name: it displays the instrument used for delta hedging and its settings;

- Hedge Order Direction: the user can choose the direction of order used to hedge the delta: Long, Short e Long & Short. This think is useful when options are used to hedge ;
- Contract Delta: it represents the delta value expressed in euro of one contract;
- Hedge Priority: The user can choose between Macro Adjustment and Fine Adjustment. Depending on the choice made by the user in the system will give priority to instruments indicated by Macro Adjustment to neutralize much of the delta and then use the instrument marked with Fine Adjustment to refine the delta hedging. If multiple instruments is associated with the same priority (Macro Adjustment and Fine Adjustment) the system will balance the delta dividing it evenly among the instruments. The most common use is to use futures as Macro Adjustment and stocks as Fine Adjustment;
- Hedge Price Type: the user can choose the type of order to use between Market, Join, Improve, Split, Shave, Hit & Take, Hit & Take +. For the description of [Orders Type](#), click [qui](#);
- Hedge Use Smart Move: the Smart Move system allows the sending of an order and the automatic change pf the price if it is not executed;
- Hedge Smart Move Step (Ticks):it represents the price change between an order and the subsequent expressed in ticks. User needs to write the ticks quantity, conversion to currency or points be automatically carried out based on security ticks settings in [Symbol Manager](#). For more informations on [Smart Move](#), click [here](#);
- Hedge Smart Move Interval (Secs): It represents the interval of time between an order and the next. For more informations on [Smart Move](#), click [here](#);
- Order Placement Mode: Here you choose how Iceberg must manage the delta hedging orders. Suggest Only: in this case the generation of an order in Iceberg is reported on the General tab, and the pending order is finalized in [Real Market](#) o [Paper Trading](#). Paper Trading (Automatic): In this case the generation of an order it is automatically finalized Paper Trading. Real Market (Manual): in this case the generation of an order appears the book corresponding to sending the order in Real Market. Real Market (Automatic): In this case the generation of an order is automatically sent to the broker with the price of the type previously set. **For any order, generation is conditioned to Date Filters.**

Frequency



This section allows to set the control frequency of the strategy's delta, or the system will calculate delta.

Min. Delta Protect Thresholds: allows you to set a threshold for the value of the delta to be protected, so not delta to 0, but for example +/- 50 €. The system will keep the strategy delta within the set

threshold. As soon as the delta exceeds the threshold (positive or negative), the delta will be brought to 0 and the set thresholds will revert to +/- 50 € in the example.

Mode:

- Contracts: the system hedge the delta only after the specify number of contract definite in Hedge Min. Quantity is reached. It is possible to choose the minimum amount for every instrument;
- Time Interval: the system checks whether is necessary hedge the delta every Time Interval (minutes);
- Time of Day: The system checks whether is necessary hedge the delta in a determined hour of the day ;
- Price Change: The system checks whether is necessary hedge the delta after a % underlying price change .

Data Filters

There are available price filter in order to avoid problem with price exposed by the market maker .

- Max Bid/Ask Spread (Options): it verify that spread between bid and ask of the options in the strategy do not exceed a setted %;
- Tick is not Zero: It verify that last tick for every instrument of the strategy is not zero;
- Max. Tick Interval: it verify that time between a tick and the subsequent occurs within a certain time-range, for every strategy instrument;
- Check Bid/Ask (Underlyings):
- Check Last (Options):

As indicated a check on bid-ask option price price and on the last of the underlying is always effectuate in order to ensure the correct data flow between the broker and iceberg

Preview

Name	Contract Delta	Hedge Order Direction	Hedge Priority	Hedge Min. Qty	Qty	Hedge Qty
Eni SpA	1.000	Long & Short	Macro Adjustment	1	0	66
STOCK FUTURE Eni 17/0...	500.000	Long & Short	Macro Adjustment	1	0	0

Data Filters Results
No Errors

Hedging system is Disabled

Previous Next

- Hedging Type
- Legs to Hedge
- Thresholds ON / OFF
- Assets to Use
- Orders Type
- Frequency
- Data Filters
- Preview




A preview of the instruments used to hedge the delta and related quantity at market (Qty) and the quantity that should be used to neutralize the delta (Hedge Qty).

Charts






Iceberg records every hedging operation in order to premise the user to analyze the settings and to optimize the hedging strategy.




II menu - Charts

 Strategy	 Settings	 Enable Hedging	TimeFrame <input type="text" value="1 Min"/>	Leg <input type="text" value="Put @ 9550 2016-06-17"/>	Option <input type="text" value="Put @ 9550 2016-06-17"/>
Strategy	Hedging	Delta Strategy Chart	Hedge Chart	TimeFrame <input type="text" value="Daily"/>	Bars Count <input type="text" value="500"/>
				Thresholds Analysis Chart	

Strategy

	Open the submenu strategy
	It allows to create a new strategy
	It allows to open a strategy previously saved
	It allows to save the strategy actually in use
	Open the window Strategy Settings for the strategy settings

Hedging

	enable or disable Hedging
---	---------------------------

Delta Strategy Chart

Timeframe	It is possible to choose the timeframe of the graph which represents the Delta
-----------	--


Hedge Chart

Leg	It is possible to choose the instrument for delta hedging, see the graph with profit/loss and the number of contract of delta hedging
-----	---

Thresholds Analysis


Option	It is possible to choose which option of the strategy the threshold are showed on the underlying graph
Timeframe	It is possible to choose which timeframe of the underlying graph the threshold are showed
Bars Count	It is possible to choose how many bars are showed in the underlying graph

Delta Strategy



In this graph is visualized the delta value of the hedging strategy since it was activated. From the menu you can choose the time frame of the graph.

Hedge Size



This graph shows the number of contracts used in every operations of hedging since hedging was activated. From the menu Hedge chart it is possible to choose, which instrument used to hedge is displayed .

Hedge In / Outcome



With reference to the chosen instrument in hedge Chart, in this graph are represented all profit / loss related to delta hedging operations.


Thresholds Analysis



In the graph is displayed Thresholds Analysis of the historical graph of the underlying (timeframe e bars count can be selected dal menù Thresholds Analysisi Chart) with the threshold set for the selected option in the menù Thresholds Analysis Chart.

This chart is very useful to analyze the position of the thresholds setted in relation to the number of times that have been touched.

Report



A useful report, accompanied by the underlying tick chart, it provides the user a clear view on the performance of its delta hedging settings.

From: http://manuals.playoptions.it/Iceberg_old/ - **Iceberg Options Solutions**

Permanent link: http://manuals.playoptions.it/Iceberg_old/en/hedging?rev=1505999337



Last update: **2017/09/21 15:08**